Ubuntu 11 Getting Started with Suricata

INTRO:

This is a guide to install Suricata with PF_RING. This installation was completed using Virtualbox version 4.0.6 and Ubuntu iso 11.04.

Sections:

1. Basic Suricata installation and how to enable some features
2. PF_RING (capture accelerator) Suricata installation with features from Section 1
3. Suricata Configuration

Required Packages To Build Suricata:

```
sudo apt-get -y install libpcre3 libpcre3-dbg libpcre3-dev

build-essential autoconf automake libtool libpcap-dev libnet1-dev

libyaml-0-2 libyaml-dev zlib1g zlib1g-dev libcap-ng-dev libcap-ng0
```

Install Suricata as and IDS and IPS system

```
#sudo apt-get -y install libnetfilter-queue-dev libnetfilter-queue1
libnfnetlink-dev libnfnetlink


# cd /opt

# wget http://www.openinfosecfoundation.org/download/suricata-1.0.5.tar.gz

# tar -xvfz suricata-1.0.5.tar.gz

# cd suricata-1.0.5

#sudo ./configure  --enable-nfqueue

#sudo make

#sudo make install
```

To install enable additional features of Suricata , install the following packages and append the ./configure line as stated:

To enable HTP Library(HTML pre-processor):

```
#apt-get install htp

./configure --with-libhtp-libraries
```

To enable libcap_ng (dropping privileges) :

```
#apt-get install libcap-ng-dev

./configure  --with-libcap_ng-libraries=/usr/lib
```

2. PF_RING installation

This installation will install PF_RING as well as enable the above features.

2.1 Download the required packages:

```
#apt-get install build-essential libpcre3-dev libpcap-dev libnet1-dev
libyamldev libnetfilter-queue-dev zlib1g-dev htp subversion flex bison linux-
headers-2.6.32-5-686 dkms libcap-ng-dev
```

Note This installation was done with linux-headers-3.0.0-12 and linux-headers-3.0.0-12-generic. Using linux-headers-2.6.32-5 caused issues while building the e1000e-pf_ring module

2.2 Download PF_RING

```
# cd /usr/src
# svn --force export https://svn.ntop.org/svn/ntop/trunk/PF_RING/
PF_RING_CURRENT_SVN
# mkdir /usr/src/pf_ring-4
# cp -Rf /usr/src/PF_RING_CURRENT_SVN/kernel/* /usr/src/pf_ring-4/
```

2.3 Configure PF_RING Driver

```
# cd /usr/src/pf_ring-4/

# nano dkms.conf
```

PACKAGE_NAME="pf_ring"
PACKAGE_VERSION="4"
BUILT_MODULE_NAME[0]="pf_ring"
DEST_MODULE_LOCATION[0]="/kernel/net/pf_ring/"
AUTOINSTALL="yes"

```
Then press CRTL+X, Y, enter

# dkms add -m pf_ring -v 4
# dkms build -m pf_ring -v 4
# dkms install -m pf_ring -v 4
```

At the end the install command you should get DKMS: INSTALL Completed

NOTE To remove the pf_ring driver, type the following command:

```
#sudo dkms remove –m pf_ring –v 4  --all
```

2.4 Configure PF_RING Aware Driver

```
# mkdir /usr/src/e1000e-pf_ring-1.3.6

# cp -Rf
/usr/src/PF_RING_CURRENT_SVN/drivers/PF_RING_aware/intel/e1000e/e1000e-
1.3.6/src/* /usr/src/e1000e-pf_ring-1.3.6/

# cp -f /usr/src/PF_RING_CURRENT_SVN/kernel/linux/pf_ring.h
/usr/src/e1000epf_ring-1.3.6/

# cd /usr/src/e1000e-pf_ring-1.3.6/

# sed -i –e
's/\.\/\.\.\/\.\.\/\.\.\/\.\.\/\.\.\/kernel\/linux\/pf\_ring\.h/pf\_ring\.h
/' netdev.c

#nano dkms.conf
```

PACKAGE_NAME="e1000e-pf_ring"
PACKAGE_VERSION="1.3.6"
BUILT_MODULE_NAME[0]="e1000e"
DEST_MODULE_LOCATION[0]="/kernel/drivers/net/e1000e/"
AUTOINSTALL="yes"

```
#dkms add -m e1000e-pf_ring -v 1.3.6
```

2.5 Install PF_RING

```
#sudo cp -f /usr/src/PF_RING_CURRENT_SVN/kernel/linux/pf_ring.h
/opt/PF_RING/include/linux/

#cd /usr/src/PF_RING_CURRENT_SVN/userland/lib

#sudo ./configure  --prefix=/opt/PF_RING/

#sudo cp -f pfring_e1000e_dna.h /opt/PF_RING/include

#sudo make

#sudo make install
```

2.6 Install libpcap with PF_RING

```
# cd /usr/src/PF_RING_CURRENT_SVN/userland/libpcap-1.1.1-ring

# sed -i –e 's/\.\.\/lib\/libpfring\.a/\/opt\/PF_RING\/lib\/libpfring\.a/'
Makefile.in

#./configure --prefix=/opt/PF_RING

#sudo make

#sudo make install
```

2.7 Install tcpdump with PF_RING

```
.# cd /usr/src/PF_RING_CURRENT_SVN/userland/tcpdump-4.1.1

# sed -i -e 's/\.\.\/lib\/libpfring\.a/\/opt\/PF_RING\/lib\/libpfring\.a/'
Makefile.in

# sed -i -e 's/-I \.\.\/libpcap-1\.0\.0-ring/-I \/opt\/PF_RING\/include/'
Makefile.in


# sed -i -e 's/-L \.\.\/libpcap-1\.0\.0-ring\/-L /\/opt\/PF_RING\/lib\//'
Makefile.in

# ./configure LD_RUN_PATH="/opt/PF_RING/lib:/usr/lib:/usr/local/lib"
--prefix=/opt/PF_RING/ --enable-ipv6

#sudo make

#sudo make install
```

3. Suricata Configuration

3.1 A The Stable version:

```
# cd /opt
# wget http://www.openinfosecfoundation.org/download/suricata-
1.0.5.tar.gz
# tar xvfz suricata-1.0.5.tar.gz
# cd suricata-1.0.5
Sudo ./configure --enable-pfring --with-libpfring-
libraries=/opt/PF_RING/lib
--with-libpfring-includes=/opt/PF_RING/include --with-
libpcaplibraries=/opt/PF_RING/lib --with-libpcap-
includes=/opt/PF_RING/include
```

```
LD_RUN_PATH="/opt/PF_RING/lib:/usr/lib:/usr/local/lib"
--prefix=/opt/PF_RING/ --enable-nfqueue --with-libcap_ng-
libraries=/usr/lib -–with-libhtp-libraries
# sudo  make
# sudo make install
```

3.1B Beta Version

```
cd /usr/src/PF_RING_CURRENT_SVN/userland/
sudo git clone git://phalanx.openinfosecfoundation.org/oisf.git
oisfnew
cd oisfnew
sudo ./autogen.sh
sudo ./configure --enable-pfring --with-libpfring-
libraries=/opt/PF_RING/lib --with-libpfring-
includes=/opt/PF_RING/include --with-libpcap-
libraries=/opt/PF_RING/lib --with-libpcap-
includes=/opt/PF_RING/include
LD_RUN_PATH="/opt/PF_RING/lib:/usr/lib:/usr/local/lib" --
prefix=/opt/PF_RING/ --enable-nfqueue --with-libcap_ng-
libraries=/usr/lib -–with-libhtp-libraries
# sudo  make
# sudo make install
```

3.2 Configure Suricata

```
#mkdir  /etc/suricata
#mkdir  /var/log/suricata
```

3.2A Stable Version:

```
#sudo cp /opt/suricata/suricata.yaml classification.conf /etc/suricata
```

3.2B Beta Version:

```
#sudo cp /usr/src/PF_RING_CURRENT_SVN/userland/lib/oisfnew
suricata.yaml classification.config /etc/surciata
```

3.3 Adding Rules to Suricata

See Suricata Wiki:
https://redmine.openinfosecfoundation.org/projects/suricata/wiki/Rule_Management_with_Oinkmaster

3.4.Run Suricata:

```
#sudo /opt/PF_RING/bin/suricata  –c  /etc/suricata/suricata.yaml –i
eth0
```